## Enrolling a Device

1. Before you begin, make sure your laptop is logged onto the **BroncoWiFi** network. Password is **gosantaclara.**
2. Connect your computer to BroncoWiFi, then navigate to https://safeconnect.scu.edu:8443/enroll
3. Enter in your Network username and password and agree to the acceptable use policy. Click **Submit**.
4. **Make sure your device you have chosen to enroll is turned on and connected to the network.**
5. An enrollment form will pop up, like the one below. Fill out the information needed, providing a MAC address and the device type. **MAC address and device type are required.**

SANTA CLARA UNIVERSITY
Enroll a Game Console or Media Device
Before continuing, be sure your device is connected to the network, active and generating traffic.
Click Here To Read Our Full Policy
Novell ID:
Password:
I accept the acceptable use policy.
Submit
Warning: Device enrollment is intended for devices that do not have browser capabilities.
Attempting to register other devices might result in loss of access and or disciplinary action.

6. Fill out an email address and mobile number. Click **Add the entry**.
7. The device status will now appear on the bottom of the selection page.
8. You may only enroll three devices.

## Additional Information

Go to it.scu.edu for more information on wireless access, setting up email, configuring mobile devices, printing, and more.

### Regular Academic Hours

Monday-Thursday: 7:30 a.m. - Midnight
Friday: 7:30 a.m. - 8:00 p.m.
Saturday: 10:00 a.m. - 8:00 p.m.
Sunday: 10:00 a.m. - Midnight

Santa Clara University

### Technology Help Desk

Santa Clara University
500 El Camino Real
Santa Clara, Ca 95053

Contact us at:
(408) 554-5700
techdesk@scu.edu
www.scu.edu/it

Follow us @scu_tech

# Santa Clara University

## Academic Technology

# Enrolling a Game Console or Streaming Media Player for Campus Use

*Technology Help Desk*

*Revised August, 2015*

## Wii MAC Address

1. Click on the **Wii** icon on the lower left corner.
2. Select **Wii Options** on the Following screen.
3. Click the right arrow to advance to the Wii **System Settings 2** page.
4. Select **Internet**.
5. Select the **Console Information**. The MAC address will then be displayed.

## Wii U MAC Address

1. From the Wii U Menu, select **System Settings**.
2. Using the Left Stick select the **Internet** icon and press the A Button.

3. Using the Left Stick select the **View MAC Address** and wait a moment for the MAC address to be displayed.




4. When you are finished, tap **Back**.

## Xbox360 MAC Address

1. Scroll down (if necessary) to **My Xbox**.
2. Select the far right tab labeled **System**.
3. Select **Network Settings**. Then select **Configure Network**.

4. Under **Basic Settings**, check to make sure the **IP Settings** is on **Automatic**.
5. Go right and select the **Additional Settings** tab.
6. Go down and select the second item **Advanced Settings**.
7. Toward the bottom of the screen, the **Wired MAC Address** should be present. This is what you need to register the device.




## Xbox One MAC Address

1. Navigate to the Settings page.
2. Select **Network**.
3. Select **Advanced Settings**.
4. MAC address will be listed next to Wired MAC on the right hand side of the screen.

## PS3 MAC Address

1. Go to the main menu and select **Settings**.
2. Select **Network Settings**.
3. Select Settings and **Connection Status List**.
4. Scroll down and the MAC Address will be displayed.




## PS4 MAC Address

1. Navigate to the **Settings** icon (located on the far left).
2. Select the **System** icon under the Settings menu.
3. Select **System Information**.
4. Scroll down and the MAC Address will be displayed.

## Streaming Media MAC Address

As these device types differ greatly, you should consult the device's manual in order to determine the MAC address. If you do not have the device's manual, go to the manufacturer's website for more information.

**If you have a new device that is not recognized, bring the device and the user manual to the Technology Help Desk for help with enrollment.**